
## DoSA-2D User Manual


**Linear Vibrator Example** 



2022-03-19 GiTae Kweon (zgitae@gmail.com)

## **DoSA Structure**

#### **Program Structure**



#### **Toolbar**

#### 1. Operations

✓ New : Create a new design

✓ Open : Open previous design

✓ Save : Save the design


✓ SaveAs : Save in different name

#### 2. Part Design

✓ Coil : Add a coil and specification design

✓ Magnet : Add a magnet and determine specifications

✓ Steel : Add a steel and determine specifications





#### 3. Virtual Test

✓ Force : Magnetic force estimation

✓ Stroke : Magnetic force estimation for each stroke

✓ Current : Magnetic force estimation for each current






# Analysis Model

## **Analysis Model**

#### 1. Shape Model



#### 2. Product Specifications

가. Coil

• Coil Turns : 126 turns

• Coil Resistance: 15.75 Ohm

나. Magnet

• Material : N52 (NdFeB 52)

• Magnetization Direction: 90 (UP)

다. Power

• Voltage: 2.5V

(Example Files: DoSA-2D Install directory > Samples > LV)




### New design

1. Toolbar > Click New button


2. Design Name: "LV"

3. Click OK









# Part Design

#### Add a coil

1. Toolbar > Click Coil button

2. Coil Name: "coil"

3. Input the coil shape

✓ Coil Location: Base\_X 1.5, Base\_Y -0.67

✓ Left-down point : X 0, Y 0

(Relative coordinates)


✓ Right-Up Point : X 0.365, Y 1.18

(Relative coordinates)


4. Screen Adjustment : Use Fit All button


5. Click OK button

6. Check shape (FEMM Window)









#### **Coil Design**

1. Input the coil instrumental specifications

✓ Coil Wire Grade : Bonded\_IEC\_Grade\_1B

✓ Copper Diameter: 0.045

✓ Horizontal Coefficient : 0.95 (Bonded Type)


✓ Vertical Coefficient : 1.13 (Bonded Type)


✓ Resistance Coefficient : 1.1 (Bonded Type)

2. Calculate the coil specification

✓ Click the "Coil Design" button

3. Check the coil specification







#### Add a magnet

1. Toolbar > Click Magnet button

2. Magnet Name: "magnet"

3. Magnet Shape

✓ Magnet location : Base\_X 0, Base\_Y 0.4

✓ Left-down Point : X 0, Y 0

(Relative Coordinates)


✓ Right-Up point : X 1.35, Y 1.0


(Relative Coordinates)


4. Screen Adjustment: Use Fit All button

5. Click OK button

6. Confirm Shape (FEMM window)










### **Magnet Settings**


1. Magnet Settings

✓ Part Material : N52

✓ Direction : UP

✓ Moving Parts : MOVING





#### Add a plate

1. Toolbar > Click Steel Button

2. Steel Name: "plate"

3. Face Type: **RECTANGLE** 

4. Plate Shape

✓ Plate location : Base\_X 0, Base\_Y 0.2

✓ Left-down point : X 0, Y 0

(Relative Coordinates)


✓ Right-Up point : X 1.35, Y 0.2

(Relative Coordinates)


5. Screen Adjustment: Use Fit All button


6. Click OK button

7. Shape confirm (FEMM window)










#### Add a yoke

- 1. Toolbar > Click Steel Button
- 2. Steel Name: "yoke"
- 3. Add input lines of point
  - ✓ Click the 'A' button four times
- 4. Yoke Shape
  - ✓ Yoke location: Base\_X 0, Base\_Y 0.2
  - ✓ 1 Point: X 0, Y 1.4
  - ✓ 2 Point : X 0, Y 1.2
  - ✓ 3 Point : X 1.9, Y 1.2
  - ✓ 4 Point: X 2.05, Y 1.05
  - ✓ 5 Point: X 2.05, Y 0
  - ✓ 6 Point : X 2.25, Y 0
  - ✓ 7 Point: X 2.25, Y 1.05
  - ✓ 8 Point : X 1.9, Y 1.4
- 5. Screen Adjustment: Use Fit All button





#### Add a yoke


6. Add the Arc Shape


✓ 3 Point : Arc, Dir check


✓ 7 Point : Arc check

7. Click OK button

8. Shape confirmation (FEMM window)









#### Plate, Yoke settings

1. Click the plate in the treeview

2. Plate settings

✓ Part Material : 430 Stainless Steel

✓ Moving Parts : MOVING


3. Click the yoke in the treeview


4. Plate settings


✓ Part Material: 430 Stainless Steel

✓ Moving Parts: MOVING

#### [BH curve]











## Virtual Test


### Test of the magnetic force

- 1. Toolbar > Click Force Button
- 2. Force Test Name: "force"
- 3. Click OK button
- 4. Settings of magnetic force test
  - ✓ Voltage: 2.5
- 5. Click "Force Test" Button














#### Results of the magnetic force

- 6. Force: -0.05515 N
- 7. Magnetic Density
  - ✓ Click the B Magnitude button
- 8. Vector of Magnetic Density
  - ✓ Click the B Vector button









### Test of the stroke-magnetic force

1. Toolbar > Click Stroke button

2. Stroke Test Name: "stroke"

3. Click OK button


4. Settings of the test


✓ Voltage: 2.5


✓ Initial Stroke: -0.5

✓ Final Stroke: 0.5

✓ Step Count: 5










### Results of the stroke-magnetic force

5. Click "Stroke Test" button



#### Test of the current-magnetic force

1. Toolbar > Click Current button

2. Current Test Name: "current"

3. Click OK button


4. Test settings


✓ Initial Current: 0.0

✓ Final Current: 0.1

✓ Step Count: 5










## Results of the current-magnetic force

5. Click "Current Test" button





# Tips

#### Open design

- 1. Toolbar > Click Open Button
- 2. Double click the design directory.
- 3. Double click the design file.







## Thank You

Email: zgitae@gmail.com

Homepage: http://openactuator.org