
DoSA-2D User Manual

Voice Coil Motor Example


(Speaker, Auto-Focus, Linear Vibrator)



2022-05-06 zgitae@gmail.com

DoSA Structure

Program Structure



Toolbar

1. Operations


✓ New : Create a new design

✓ Open : Open previous design

✓ Save : Save the design

✓ SaveAs : Save in different name

✓ Import : DXF Import



2. Part Design

✓ Coil : Add a coil and specification design

✓ Magnet : Add a magnet and determine specifications

✓ Steel : Add a steel and determine specifications



3. Virtual Test

✓ Force : Magnetic force estimation

✓ Stroke : Magnetic force estimation for each stroke

✓ Current : Magnetic force estimation for each current






Work process

Product Design


Virtual Test



Analysis Model

Analysis Model

1. Shape Model



2. Product Specifications

가. Coil

• Coil Turns : 126 turns

• Coil Resistance: 15.75 Ohm

나. Magnet

Material: N52 (NdFeB 52)

• Magnetization Direction: 90 (UP)

다. Power

Voltage: 2.5V

(Example Files : DoSA-2D Install directory > Samples > VCM)




New design


1. Toolbar > Click New button

2. Design Name: "VCM"

3. Click OK









Import shapes


- 1. Toolbar > Click New button
- 2. Select "VCM.dxf" and click the Open button
- 3. Check part shapes

[Caution for the Shape Model]

- Part must be written in Polyline
- Please refer to "Drawing Guide"
- https://solenoid.or.kr/data/Drawing Guide ENG.pdf









Part Design


Set as Coil


1. Treeview > "DXF_Shape_2" double click

2. Change name: "coil"

3. Change part type: COIL

4. Click OK button







Coil Design

Select the magnetic force calculation part

1. Input the coil instrumental specifications

✓ Moving Parts : MOVING

✓ Coil Wire Grade : Bonded_IEC_Grade_1B

✓ Copper Diameter: 0.045

✓ Horizontal Coefficient : 0.95 (Bonded Type)

✓ Vertical Coefficient : 1.13 (Bonded Type)


✓ Resistance Coefficient : 1.1 (Bonded Type)

2. Calculate the coil specification


✓ Click the "Coil Design" button


3. Check the coil specification

4. Ribbon Bar > Save












Set as Magnet


1. Treeview > "DXF_Shape_1" double click

2. Change name: "magnet"

3. Change part type: MAGNET

4. Click OK button







Magnet Settings

1. Magnet Settings

✓ Part Material : N52

✓ Direction : UP






Set as Plate


1. Treeview > "DXF_Shape_3" double click

2. Change name: "plate"

3. Change part type: STEEL

4. Click OK button






Set as Yoke


1. Treeview > "DXF_Shape_4" double click


2. Change name: "yoke"

3. Change part type: STEEL

4. Click OK button









Virtual Test


Test of the magnetic force

- 1. Toolbar > Click Force Button
- 2. Force Test Name: "force"
- 3. Click OK button
- 4. Settings of magnetic force test
 - ✓ Voltage: 2.5
- 5. Click "Force Test" Button














Results of the magnetic force

- 6. Force: 0.05614 N
- 7. Magnetic Density
 - ✓ Click the B Magnitude button
- 8. Vector of Magnetic Density
 - ✓ Click the B Vector button







Test of the stroke-magnetic force

1. Toolbar > Click Stroke button

2. Stroke Test Name: "stroke"

3. Click OK button


4. Settings of the test


✓ Voltage: 2.5


✓ Initial Stroke: -0.5

✓ Final Stroke: 0.5

✓ Step Count: 5










Results of the stroke-magnetic force

5. Click "Stroke Test" button



Test of the current-magnetic force

1. Toolbar > Click Current button

2. Current Test Name: "current"

3. Click OK button


4. Test settings


✓ Initial Current: 0.0

✓ Final Current: 0.1

✓ Step Count: 5










Results of the current-magnetic force

5. Click "Current Test" button





Tips

Open design

- 1. Toolbar > Click Open Button
- 2. Double click the design directory.
- 3. Double click the design file.







Thank You

Email: zgitae@gmail.com

Homepage: http://openactuator.org